

How do I connect to Remote1 terminal server from off campus?

Remote Desktop Connection


Windows 8/Vista/XP

10/19/2011


Use the Remote Desktop Connection software on your Windows Operating System to connect to the Remote1 terminal server from off campus. Access to the Remote1 terminal server will allow you the ability to use Microsoft Office, access your G:\ and Q:\ drive folders and check your e-mail using the Outlook client. The following instructions follow a Windows 8 setup, although similar steps can be done for previous Windows versions.

Note: All JC Administrators and Faculty have access to use this service. JC Staff must obtain authorization through their immediate supervisor and the Human Resources department.


Step 1: Select Remote Desktop Connection at the Windows 8 Start screen.



Step 2: Click **Show Options**.



Step 3: Under the *General* tab type **remote1.jccmi.edu** in the *Computer* field. Enter your JCC network username in the *User name* field.



Logon settings

Enter the name of the remote computer.


Computer: remote1.jccmi.edu

User name: chipsjohnc

You will be asked for credentials when you connect. To use the current user credentials, clear the following check box.


Always ask for credentials

Step 4: Click **Experience** tab.



General Display Local Resources Programs Experience Advanced

Step 5: Choose your internet connection speed from the drop down list.



Performance

Choose your connection speed to optimize performance.


High-speed broadband (2 Mbps - 10 Mbps)

Allow the following:

- Desktop background
- Font smoothing
- Desktop composition
- Show window contents while dragging
- Menu and window animation
- Visual styles
- Persistent bitmap caching


Note: Examples of *high-speed broadband connections* are Comcast cable, AT&T DSL, etc. If you are unsure of your internet connection speed select Modem (56 Kbps).

Step 6: Click **Advanced** tab.



General Display Local Resources Programs Experience Advanced

Step 7: Under *Connect from anywhere* click **Settings**.



Server authentication

Server authentication verifies that you are connecting to the intended remote computer. The strength of the verification required to connect is determined by your system security policy.

If server authentication fails:

Warn me


[What are my server authentication options?](#)

Connect from anywhere

Configure settings to connect through Remote Desktop Gateway when I am working remotely.

Settings...

Step 8: Select **Use these RD Gateway server settings**.



Connection settings

Automatically detect RD Gateway server settings

Use these RD Gateway server settings:


Server name:

Logon method: Allow me to select later

Bypass RD Gateway server for local addresses

Do not use an RD Gateway server

Step 9: Enter **remote1.jccmi.edu** in the Server name field. Check **Bypass RD Gateway server for local addresses**.



Connection settings

Automatically detect RD Gateway server settings

Use these RD Gateway server settings:


Server name: remote1.jccmi.edu

Logon method: Allow me to select later


Bypass RD Gateway server for local addresses

Do not use an RD Gateway server

Step 10: Check **Use my RD Gateway credentials for the remote computer.**




Step 11: Click **General** tab.




Note: The following steps (12 & 13) will save the above connection settings to your local machine (or location of your choosing). You will only need to save the connection settings once.


Step 12: Click **Save As...**



Step 13: Click **Desktop**. Enter **JCC Remote1 Access.rdp** in the File name field. Click **Save**.



Congratulations! You have successfully configured your computer to connect to the Remote1 terminal server. From this point forward double-click the **JCC Remote1 Access.rdp** icon to access this service.



You may receive the following message after double-clicking JCC Remote1 Access.rdp. This message is asking you to verify the server that you are about to connect to. Please verify **remote1.jccmi.edu** is listed as the *Remote computer* and *Gateway server*. Check **Don't ask me again for connections to this computer**. Click **Connect**.

